#### **ED KING**

Agricultural Commissioner/ Sealer of Weights and Measures

#### **PRISCILLA YEANEY**

Assistant Agricultural Commissioner/ Sealer of Weights and Measures

# AGRICULTURAL COMMISSIONER SEALER OF WEIGHTS AND MEASURES



### **OFFICE LOCATION:**

2543 Cordelia Road Fairfield, CA 94534

### **MAILING ADDRESS:**

675 Texas Street Fairfield, CA 94533

Phone (707) 784-1310 Fax (707) 784-1330 www.solanocounty.com

## CONDITIONS COVERING THE USE OF PESTICIDES NEAR SENSITIVE SITES

The Commissioner defines sensitive sites as areas frequented by people and environmentally sensitive areas that could suffer harm or injury. Sensitive sites include:

- Rural and/or residential homes
- Farmworker housing
- Schoolsites
- Hospitals, nursing homes
- Organic operations

- Sensitive crops
- Lakes, ponds, waterways, estuaries, reservoirs
- Livestock, beehives
- State Wildlife Management Areas
- Critical habitats of endangered or threatened species

If hazards to endangered species are indicated on a label, check with the California Department of Pesticide Regulation's PRESCRIBE, an online endangered species database for further information.

## http://calpip.cdpr.ca.gov/infodocs.cfm?page=aboutprescribe

WARNING or DANGER materials may not be applied unless the buffer distance between closest operating nozzle and non-target areas are maintained as listed below. The use of CAUTION materials and/or alternative application measures should be considered as mitigation efforts. Buffer distances shall be measured from the edge of the area that could be reasonably used by the resident (for example the yard edge).

In order to apply pesticides closer than the buffer distance, the permittee shall obtain written permission by the occupant of the dwelling. This written permission must also be provided to the Pest Control Business performing the application prior to the start of the application. A copy of the written permission shall be made available upon request by the Commissioner.

Buffer distances shall be maintained to prevent exposure to occupants in proximity to rural residential properties; i.e. a single home on or adjacent to agricultural farming operations. This includes residences rented or leased for occupancy by the property operator(s).

Air movement shall be away from the sensitive sites noted above at all times during an application regardless of the required buffer distance.

# Sensitive Site Buffer Distance Table

# **TYPE OF PESTICIDE APPLICATION EQUIPMENT**

# **BUFFER DISTANCE BETWEEN CLOSEST OPERATING NOZZLE AND THE NON-TARGET AREA**

100 feet (or in compliance w/ fumigation

Aircraft 500 feet Danger, 300 feet Warning

Air blast orchard sprayer 100 feet

100 feet High boom ground rig in open field use

Ground rig applying liquid or dust 100 feet formulations of pesticide no more than 12

inches above the soil

Ground rig applying liquid or gas below soil (see also fumigation requirements if

applicable)

regulations, whichever is more restrictive)

Ground rig applying dry pesticide pellets no more than 12 inches above the soil or below the soil

5 feet